




NETWORK INSTALLATION INSTRUCTIONS – VERSION XVII

To install the network version of Statgraphics Centurion XVII:

1. Select a location to install the program where all users can access the main executable and sample data files.
2. Download and install the desired edition from the Download Center at www.statgraphics.com in that location. It is a standard Windows installation.
Note: there is only one download for both the single-user and network editions.
3. From a CLIENT, locate the executable *sgwin.exe* that was created when the program was installed.
4. With administrator rights, execute *sgwin.exe*.
5. Push the *Activate* button when the following dialog box appears:



6. Complete the fields on the License Manager dialog box shown below, including the serial number:

STATGRAPHICS Centurion Activation

StatPoint Technologies, Inc.

Step 1: To activate the program, first enter the following information (* required):

*Last name: Last name *First name: First name

*Organization: Organization

*E-Mail: purchaser@mycompany.com

Address:

Address:

City: State:

*Country: United States of America Postal Code:

*Phone: 540-555-5555 Fax:

Product key: Request: Request activation code.

*Serial number: ABCD-EFGH-IJKL-MNOP-QRST

Step 2: Use either of the following 2 ways to request an activation code:

to submit request over the Internet (recommended - automated response).

to request an activation code via E-mail (requires manual response).

Step 3: When you receive your activation code by return e-mail, enter it below and press the Activate button:

NETWORK LICENSES ONLY: If license file (sgc.usr) exists in another location, enter directory:

If you enter a valid serial number, the *Product key* field will be populated with a unique value.

7. Press one of the “*Press Here*” buttons to receive an activation code via e-mail or call 540-428-0084 and ask for “Support”. The first button will only work if you enter the email address supplied when the program was purchased.
8. Enter the activation code and press “Activate”. You should see a dialog box indicating that the activation code has been accepted. Press OK to launch the program.
9. Create shortcuts on each client to *sgwin.exe*. No activation is required on the clients.

NOTES

- Nothing runs on the server. It simply acts as a shared location for the program files. It requires approximately 250MB of disk space.

- The program runs in the memory space of the clients. The minimum RAM in each client is 512MB, although more is recommended if analyzing large amounts of data.
- The 32-bit version will run on both 32-bit and 64-bit clients. The 64-bit version will only run on 64-bit clients. Since nothing runs on the server, the only server requirement is space on a shared disk.
- The activation process creates a main license file named *sgc.usr* which is a text file containing the serial number, product key, and activation code. It also creates small files named “sguser1.log”, “sguser2.log”, etc. which control the number of simultaneous users.
- The activation code entered must match the Product Key displayed on the License Manager dialog box, which is different for each installation.
- The field at the very bottom of the License Manager dialog box is not normally used. It can be used if you wish to install the executable in 2 locations and share a single license file. If so, complete the first installation as described above. Then install the program again in a second location. When you activate the second installation, use the extra field to specify the location in which the FIRST installation placed its license files.

For help, please mail support@statgraphics.com or call 1-800-232-7828 or 1-540-428-0084 and ask for “Support”.